





Screen Keybindings

Screen manager with VT100/ANSI terminal emulation

Precede all commands by **^A** (+A)¹

'	Switch to window name/number	p ^h		Switch to previous window ³
"	Show window list	q		Send literal ^Q (XON) to current window)
0..9	Switch to window 0..9	Q		Delete all but the current region
-	Switch to the blank window	r		Toggle line-wrap for current window ³
	Switch input focus to next region	S		Send literal ^S (XOFF) to current window ³
^a	Switch to previous window ²	S		Split current region horizontally
a	Send literal ^A (SOH) to window	t		Show load average and xref ³
A	Name current window	v		Show version and compilation date
b	Send break to window ³	^v		Enter digraph
B	Reopen terminal line and send break	w		Show active window list ³
c	Create and switch to new window with a shell ³	W		Toggle between 80 and 132 columns
C	Clear the screen	X		Lock terminal ³
d	Detach screen from this terminal ³	X		Kill current region
D	Detach and logout	Z		Suspend <i>screen</i> ³
f	Toggle flow between on, off, auto ³	Z		Reset virtual terminal values
F	Resize window to current region size	.		Dump termcap to .termcap
^g	Toggle visual bell	?		Show key bindings
h	Capture current window to hardcopy.n	^\ :		Kill all windows and terminate <i>screen</i> Enter a command line
H	Toggle logging of current window to screenlog.n	:		Enter a command line
i	Show info about current window ³	[		Enter copy/scrollback mode ³
k	Destroy current window ³]		Write paste buffer to current window's <i>stdin</i> ³
l	Refresh current window ³	{ }		Copy and paste previous command line
L	Toggle login state for current window	>		Write paste buffer to screen-exchange file
m	Repeat last message in message line ³	<		Read screen-exchange file into paste buffer
M	Toggle monitoring of current window	=		Delete screen-exchange file
	Switch to next window ³	,		Show copyright page
N	Show number and title of current window	-		Toggle inactivity monitoring for current window
*	Show list of attached displays			Split current region vertically

Notes

- ¹ Command character is **^A** by default. Override with the `-e` option
- ² Command character typed twice by default (e.g., becomes **]]** if the command character is set to **]** using the `-e` option)
- ³ Commands bound to lowercase letters are bound to their control character counterparts (e.g., **^A c** is equivalent to **^A ^c**)